

SERVER Process Events

1100

ERROR *object* discarded event *event-type*.

Cause

An internal error occurred which caused an event to be discarded.

Effect

The effect is unknown.

Recovery

This error should n be reported to the LightWave Client system administrator.

1110

ERROR *port-type* port *tcpip-process:port* bind failed, error *reason*

Cause

An error occurred binding to the TCP/IP port due to the indicated reason.

Effect

The port cannot start.

Recovery

Correct the underlying condition if possible. An attempt will be made to automatically restart the port.

1111

ERROR *port-type* port *tcpip-process:port* accept failed, error *reason*

Cause

An error occurred accepting a connection on the TCP/IP port due to the indicated reason.

Effect

The connection fails.

Recovery

Correct the underlying condition if possible.

1112

ERROR *port-type* port *tcpip-process:port* listen, error *reason*

Cause

An error occurred binding to the TCP/IP port due to the indicated reason.

Effect

The port cannot start.

Recovery

Correct the underlying condition if possible. An attempt will be made to automatically restart the port.

1113

ERROR Start of *port-type* port *tcpip-process:port* failed, retry in 15 seconds

Cause

A port restart has been scheduled due to an error.

Effect

The port is stopped and will be restarted.

Recovery

None.

1114

ERROR IO error *filesystem-error* occurred on *port-type* port *tcpip-process:port*, the port will restart.

Cause

An I/O error occurred on the port.

Effect

The port will be restarted.

Recovery

Correct the underlying condition if possible. An attempt will be made to automatically restart the port.

1115

ERROR *port-type* port *tcpip-process:port* create socket failed, error *error-number*: *reason*

Cause

An error occurred while attempting to create a socket due to the indicated reason.

Effect

The port cannot start.

Recovery

Correct the underlying condition if possible. An attempt will be made to automatically restart the port.

1201

ERROR The filesystem in subvolume *subvolume-name* could not be opened, *reason-for-failure*.

Cause

The filesystem in the specified *subvol-name* could not be opened for the supplied *reason*

Effect

The process cannot start.

Recovery

Correct the --filesystem startup parameter and restart the process

1202

ERROR Startup cannot continue.

Cause

An error occurred that prevents startup of the process.

Effect

The process stops.

Recovery

Correct the error and restart the process.

1205

ERROR *license-error-description*

Cause

A general license error has occurred. The *license-error-description* describes the error.

Effect

The process cannot start.

Recovery

Correct the license error and restart the process.

1226

ERROR The --monitor option value *value* is invalid. *reason*

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1229

ERROR The --diag-log option value *value* is invalid. *reason*

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1232

ERROR *tcpip-process-configuration-error*

Cause

The TCP/IP process configuration is invalid for the reason shown.

Effect

The process cannot start.

Recovery

Correct the --tcpip option value and restart the process.

1234

ERROR The --http-request-timeout option value *value* is invalid. The timeout value must be in the range *range* milliseconds.

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1237

ERROR The --blob-files option value *value* is invalid. *reason*

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1238

ERROR Error *file-system-error* occurred while attempting to create diagnostic log file *file-name*.

Cause

The indicated file system error occurred while creating a diagnostic log file. The error may be due to a volume full condition or a security violation.

Effect

The diagnostic log was not created.

Recovery

Correct the underlying condition.

1239

ERROR The --tls-options option value *value* is invalid. *reason*

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1240

ERROR The --tls-cipher-list option value *value* is invalid. *reason*

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1241

ERROR The --string-padding option value **value** is invalid. The value must be 'spaces', 'zeros', or an integer in the range 0 - 255.

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1242

ERROR The --http-proxy-host option value **value** is invalid.

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1245

ERROR The --default-encoding option value **value** is invalid. The encoding is not available.

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1246

ERROR The --tls-protocols option value **value** is invalid. **reason**

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1254

ERROR The --http-proxy-credentials option value **value** is invalid. **reason**

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1255

ERROR The --http-credentials option value **value** is invalid. **reason**

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1256

ERROR Index error for filesystem **filesystem-subvolume**. **reason**

Cause

There may be an inconsistency with the Enscribe alternate indexes references for the filesystem located in *filesystem-subvol*. Additional details are provided in *reason*.

Effect

The process cannot start.

Recovery

Correct the index issue and restart the process.

1257

ERROR The TCP/IP bind address **ip-address** is invalid. **reason**

Cause

The specified option value is invalid.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1258

ERROR *auth-config-error*

Cause

The indicated error occurred while loading the authentication configuration file.

Effect

The process cannot start.

Recovery

Correct the configuration file and restart the process.

1261

ERROR The specified license file **file-name** could not be opened, file system error: **error-description**.

Cause

The indicated file system error occurred while opening the license file.

Effect

The process cannot start.

Recovery

Correct the condition that caused the error and restart the process.

1262

ERROR The specified license file name *file-name* is invalid.

Cause

The specified file does not contain a valid product license

Effect

The process cannot start.

Recovery

Install a valid product license file.

1270

ERROR The --msg-log option must have a value.

Cause

The --msg-log option was specified without a value.

Effect

The process cannot start.

Recovery

Correct the option value and restart the process.

1271

ERROR Message logging configuration is invalid. *reason*

Cause

The message logging configuration contains a syntax error.

Effect

The process cannot start or if already running and the configuration is monitored, the configuration cannot be reloaded.

Recovery

Correct the error and restart the process or if the configuration is monitored, wait for the configuration to reload.

1272

ERROR The message logging configuration file *file-name* could not be accessed. *reason*

Cause

The message logging configuration file could not be loaded due to the indicated reason.

Effect

The process cannot start or if already running and the configuration is monitored, the configuration cannot be reloaded.

Recovery

Correct the error and restart the process or if the configuration is monitored, wait for the configuration to reload.

1274

ERROR Message logging collector **collector-name**: IO retry limit exceeded. The collector has been disabled.

Cause

Excessive errors occurred while writing events to the specified collector.

Effect

No further events will be sent to the collector.

Recovery

Correct the underlying condition and restart the process.

1275

ERROR Message logging collector **collector-name**: **io-type** start IO error: serverclass:**pathmon-name**:**serverclass-name**, error **filesystem-error**:**pathsend-error**. The I/O will be retried in **interval** seconds.

Cause

The indicated error occurred while sending an event to the collector.

Effect

The event is queued for retry.

Recovery

The process will attempt to recover from the error.

1283

ERROR Error loading log configuration from file **file-name**. reason

Cause

The process log configuration file could not be loaded due to the indicated reason.

Effect

The process cannot start or if already running and the configuration is monitored, the configuration cannot be reloaded.

Recovery

Correct the error and restart the process or if the configuration is monitored, wait for the configuration to reload.

2201

WARN **backup-takeover-message**

Cause

The backup process has taken over for the primary process for the reason indicated.

Effect

The backup process is not the primary. A new backup process will be created.

Recovery

Informational message only; no corrective action is needed.

2202

WARN Backup CPU **cpu** is down.

Cause

The configured CPU for the backup process and the process itself are down.

Effect

There is no longer a backup process running.

Recovery

When the backup cpu is restored, a new backup process will be started automatically.

2203

WARN Unable to start backup process in CPU *cpu*, *reason*

Cause

The backup process could not be started for the indicated reason.

Effect

There is no longer a backup process running.

Recovery

If possible, correct the underlying condition. The primary process will attempt to restart the backup periodically.

2204

WARN Backup CPU *cpu* is up.

Cause

This event is used for informational purposes.

Effect

A new backup process will be started.

Recovery

Informational message only; no corrective action is needed.

2206

WARN Certificate *cert-name* for *port-type* port *port-name* does not exist. Connections will be rejected until the certificate is installed.

Cause

An HTTPS port was configured but the specified certificate is not installed.

Effect

TLS connections will fail until the certificate is installed.

Recovery

Informational message only; no corrective action is needed.

2210

WARN The filesystem is *percent-value* full. Perform filesystem maintenance as soon as possible.

Cause

The filesystem is nearly full.

Effect

None.

Recovery

Perform filesystem maintenance. See [Managing the Filesystem](#)

2211

WARN The filesystem is *percent-full* full. HTTP logging has been automatically disabled.

Cause

The filesystem is nearly full and HTTP logging has been disabled.

Effect

HTTP logging has been disabled to avoid filling the filesystem.

Recovery

Perform filesystem maintenance. See [Managing the Filesystem](#)

2256

WARN Index warning for filesystem *filesystem-subvol*. *reason*

Cause

There may be an inconsistency with the Enscribe alternate indexes references for the filesystem located in *filesystem-subvol*. Additional details are provided in *reason*.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3201

INFO *component-name* - *component-version*

Cause

This event shows the product component name and version.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3202

INFO Running in CPU *cpu*.

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3203

INFO Backup process started in CPU *cpu*

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3204

INFO Stopped.

Cause

The process has stopped.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3205

INFO Opened filesystem in *filesystem-subvol*.

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3207

INFO Loading product license from *file-name*

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3216

INFO Configuration monitoring is disabled.

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3217

INFO Configuration monitoring is enabled: *monitor-config*

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3221

INFO Loaded process log configuration from file *file-name*.

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3222

INFO Process log configuration is *process-log-config*

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3229

INFO TLS cipher list: *cipher-list*

Cause

This event is used for informational purposes.

Effect

None.

Recovery

Informational message only; no corrective action is needed.

3240

INFO Shutdown started.

Cause

Process shutdown has started.

Effect

None.

Recovery

Informational message only; no corrective action is needed.